

READ ME

TAMS BASIC/UX 8.1 and BASIC Plus for HP-UX 11i

April 2007

Description

The software in the CD with the part number **T2047A-0103** contains an update to Revision 8.1 of **TAMS BASIC and BASIC Plus for HP-UX 11i**. This update includes the following changes:

- Japanese fonts can now be displayed in BASIC Plus widgets and dialogs
- Keyboard input (one-byte characters) can now be entered into BASIC Plus dialogs while in the “ja_JP.SJIS” locale

Important Note

This software supersedes Revision 8.1 of March 2006, although the revision number was not changed to minimize the impact on current users.

This READ ME file doesn't document features introduced in previous versions or RMB/UX, such as keyboard daemons, versioning, or ITF keyboard mappings. Refer to the README files of those versions for that documentation.

The TAMS I/O Libraries for HP-UX, Part Number T2091-32-64 are required to run Revision 8.1. A CD containing that software is included with this product.

Installation

The **TAMS BASIC and BASIC Plus for HP-UX 11i** CD contains two software products:

- TAMS BASIC C.08.10, and
- BASIC Plus A.01.03

BASIC Plus is an add-on product for TAMS BASIC. You may install one or both products, depending on your needs. These are the installation steps:

1. Back up your system before installing this software.
2. Login as root.
3. Mount the TAMS BASIC CD on the /SD_CDROM directory. For example:

```
mount /dev/dsk/c3t0d0 /SD_CDROM
```

4. Run the interactive version of swinstall:

```
Source Depot Type:      Local CDROM
....
Source Depot Path...   /SD_CDROM
```

5. Mark and install both products or only TAMS2047:

Marked?	Name		Revision	Information
Yes	BASIC-PLUS	→	A.01.03	HP BPLUS Revision A.01.03
Yes	TAMS2047	→	C.08.1	HP BASIC/UX

Action → Install...

Customization

For information on how to customize TAMS BASIC to your HP-UX environment, please consult the “Installing and Using RMB/UX 8.x” section of the **TAMS BASIC Documentation CD**, and the **README.JAPAN** file, which can be found in the directory `/opt/rmb/rmb8_1/newconfig` of the system where RMB/UX was installed.